


XML-Sitemaps.com 5 Minute installation Guide


Once you have purchased our unlimited PHP sitemap generator script you will receive your own individual download link for the file by email.

Click on the link and you will be presented with a screen similar to the picture below:



Click save and save the file to your PC.

Select "Open" and you will see the following:




Select "Extract all files"


Installing onto your server by FTP

Now that you have the extracted files on your PC you need to upload them to your website. In this example we are going to use Filezilla, a popular free FTP program which can be downloaded [here](#).


Open Filezilla




and enter your ftp login details: Host, Username and Password. Click the 'Quickconnect' button or hit enter on your keyboard and you will be connected to your site.



On the right hand side you can see your website's file structure. We need to install the script into your root folder which is often referred to as public_html (or www, htdocs, etc.)



Now we are in the public_html directory you simply need select the generator folder in the left hand screen with your mouse and drag it over to the window on the right. Filezilla will then copy all of the files to your website.



Once uploaded you will now see the generator folder on the right hand side of the screen.

The screenshot displays a file manager interface with two main panels: 'Local site' and 'Remote site'. The 'Local site' panel shows the local file system at 'C:\generator\'. The 'Remote site' panel shows the remote file system at '/public_html/'.

Local site: C:\generator

- Desktop
 - Windows Explorer
 - My Computer
 - C: (SYSTEM)
 - AddOn
 - BJPrinter
 - DBBackup
 - Documents and Settings
 - Downloads
 - generator

Remote site: /public_html/

- public_html
 - ._private
 - ._vti_bin
 - ._vti_cnf
 - ._vti_log
 - ._vti_pvt
 - ._vti_txt
 - cgi-bin
 - css
 - forum


Local site File List:

Filename	Filesize	Filetype	Last modified
found.001		File Folder	20/10/2005 13:13:25
generator		File Folder	03/10/2007 20:38:18
m4p2mp4		File Folder	22/01/2006 19:55:50
mp4		File Folder	22/05/2006 16:44:58
MWASPI		File Folder	23/02/2007 20:26:39
My Music		File Folder	29/12/2006 19:51:56
Nokia		File Folder	12/02/2005 12:07:00
NormanAV		File Folder	04/03/2002 10:43:50
Photoshop 5.02 (...)		File Folder	12/12/2003 15:17:28
Program Files		File Folder	06/10/2007 21:47:27


Remote site File List:

Filename	Filesize	Filetype
..		
access-logs		File Folde
etc		File Folde
generator		File Folde
logs		File Folde
mail		File Folde
public_ftp		File Folde
public_html		File Folde
tmp		File Folde
.....		File Folde


You will need to create two new blank xml files - sitemap.xml and ror.xml. An easy way to create these files is to use 'Notepad' (Start > Accessories > Notepad). In the File menu click 'Save As...' Choose 'All Files' and type in the name sitemap.xml as below. Repeat this process for ror.xml




Now you need to upload `ror.xml` and `sitemap.xml` files to the root directory by dragging the files over



We now need to set file permissions for the `ror.xml` and `sitemap.xml` files so that the script can write to them once it has run. To do this highlight `sitemap.xml` on the right hand side screen and then right click your mouse. You will be presented with a popup screen. Move your mouse down to File Attributes and select it.




You will then be given the options to change file permissions:




In the Numeric value box type 666 and then click OK. Repeat this step with the ror.xml file and set permissions to 666.

Next we need to open the generator folder.

Once done we need to set permissions for the data folder to 777



Once you have done that we need to set file permissions for the config.inc.php file to 666



Note: in case of Windows/IIS servers it is not allowed to set permissions via FTP and you will have to do that using your Hosting Control Panel.

Congratulations your installation is now complete!

To access your sitemap generator enter your website address (www.mysite.com/generator) and follow the on screen instructions.

Standalone XML Sitemap Generator

Configuration	Crawling	View Sitemap	Analyze	ChangeLog	Broken Links	Documentation
-------------------------------	--------------------------	------------------------------	-------------------------	---------------------------	------------------------------	-------------------------------

No sitemaps found

Sitemap was not generated yet, please go to [Crawling](#) page to start crawler manually or to setup a cron job.

What is "Initial URL"?

Please enter the **full** http address for your site, only the links within the starting directory will be included.

What is "Change frequency"?

This value indicates how frequently the content at a particular URL is likely to change.

What is "Last Modified"?

The time the URL was last modified. You can let the generator set this field from your server's response headers or to specify your own date and time.

What is "Priority"?

The priority of a particular URL relative to other pages on the

Configuration

Main parameters

Starting URL:

Save sitemap to:

Current path to Sitemap generator is: /home/anh0181/public_html/generator/

Your Sitemap URL:

Create Text Sitemap:
 Create sitemap in text format for Yahoo submission

Create ROR Sitemap:
 Create sitemap in ROR format
It will be stored in the same folder as XML sitemap, but with different filename: ror.xml

Create HTML Sitemap:
 Create html site map for your normal visitors
Please note that this option requires additional resources to perform

HTML Sitemap filename:

Once you have fine tuned your configuration and clicked save then go back to your config.php file within Filezilla and change permissions to 644. This is a security measure.